

MADCAP FLARE 2024 r2

Source Control: Perforce

Copyright © 2024 MadCap Software. All rights reserved.
Information in this document is subject to change without notice. The software described in this document is furnished under a license agreement or nondisclosure agreement. The software may be used or copied only in accordance with the terms of those agreements. No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or any means electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of MadCap Software.
MadCap Software 1660 17th Street, Suite 201 Denver, Colorado 80202
858-320-0387 www.madcapsoftware.com
THIS PDF WAS CREATED USING MADCAP FLARE.

CONTENTS

CHAPTER 1	
Introduction	5
CHAPTER 2	
General Information for Perforce Helix Core Common Source Control Terms Source Control Icons Bind Detection, Disabling Providers, and Unbinding	8
Providers—Perforce Helix Core	11
CHAPTER 3	
Process for Perforce Helix Core	14
Binding a Project to Perforce Helix Core	15
Importing From Perforce Helix Core	
Getting the Latest Version of Source Control Files	23
Checking Out Source Control Files	27
Submitting Source Control Files	29
Merging Source Control Files	32
CHAPTER 4	
Other Activities for Perforce Helix Core	41
Adding Files to Source Control	43

CONTENTS

Deleting Source Control Files	45
Disabling the Get Latest Prompt for Source Control	46
Disabling a Perforce Helix Core Provider	47
Disconnecting From Source Control	49
Enabling Source Control Status Checks	51
Locking a File	52
Publishing to Source Control	53
Reverting a Checkout of Source Control Files	54
Rolling Back to an Earlier Version of a File	55
Setting Color Options for Project File Differences	61
Unbinding a Perforce Helix Core Provider	63
Undeleting Source Control Files	65
Unlocking a File	66
Viewing Differences in Source Control Files	67
Viewing Files That are Checked Out	70
Viewing the History of Source Control Files	76
APPENDIX	
PDFs	78
Tutorials	78
Cheat Sheets	79
User Guides	80

CONTENTS

CHAPTER 1

Introduction

You can use the Flare interface to perform various source control tasks for a project that is bound to Perforce Helix Core.

General Information

- "Common Source Control Terms" on page 8
- "Source Control Icons" on page 9
- "Bind Detection, Disabling Providers, and Unbinding Providers—Perforce Helix Core" on page
 11

Process

- 1. Install and Set Up Perforce Helix Core (done outside of Flare)
- 2. "Binding a Project to Perforce Helix Core" on page 15
- 3. (Other Team Members) "Importing From Perforce Helix Core" on page 21
- 4. "Getting the Latest Version of Source Control Files" on page 23
- 5. "Checking Out Source Control Files" on page 27
- 6. "Submitting Source Control Files" on page 29
- 7. "Merging Source Control Files" on page 32

CHAPTER 1 5

NOTE When you remove files from your project and submit your changes, you still need to
perform a "get latest" in order for those files to be removed from the client.

NOTE If you unpack a zipped project that is bound to source control, the files in the unpacked project become editable.

CHAPTER 1 6

CHAPTER 2

General Information for Perforce Helix Core

There are various pieces of general information you should know if you plan to use this feature.

This chapter discusses the following:

Common Source Control Terms	3
Source Control Icons	Ç
Bind Detection, Disabling Providers, and Unbinding Providers—	
Perforce Helix Core	1

Common Source Control Terms

Following are definitions for some of the common phrases used in Flare's built-in source control system.

- **Bind** This means to connect your project to Perforce Helix Core. After doing this, you can then take advantage of all the automated source control tasks (such as submit, revert, lock, unlock, and so on).
- Submit This means to send changes made to your open Flare files to the server, or depot.
- Check Out This means to copy the latest source control files to your local Flare project and remove the "Read Only" designation from them so that you can edit the files.
- Get Latest Version This means to copy the latest source control files to your local project without necessarily checking out the files. This means that the "Read Only" designation will remain associated with the files until you check them out.
- Revert This means to undo changes you have made to a Flare file. Changes are reverted to the way they were at the last submit.
- Lock This means to prevent other users from submitting changes to an opened Flare file in source control.
- Unlock This means to remove an existing lock from an open Flare file so other users can submit changes to the file.

NOTE Flare integrates with multiple source control providers to provide built-in source control support. Each of the source control providers built-in to Flare uses different terms. As such, Flare's source control interface is different depending on which source control provider you use. Please refer to the sections for each source control provider if you need to see information about the terms used by other built-in systems.

Source Control Icons

Following are descriptions for the primary icons that you may see next to files when using source control.

Icon	Description
~	Checked Out
	This indicates that the file has been checked out from source control. You can submit the file when you are ready (if you are the user who has checked it out).
•	New File (Pending Add)
	This indicates that you have a file in your project but have not yet added it to Helix Core. This might occur, for example, if you create a new topic and do not add the file to source control during the topic creation process. To resolve this, simply right-click on the file and select Source Control > Add .
â	Not Checked Out
	This indicates that the file is added to source control but is not currently checked out, which means that it contains a "Read Only" designation in its properties. In order to edit the file, you must check it out from source control.
â	Locked by Another User
	This indicates that another user has locked the file. You will often see this icon in conjunction with the & icon, indicating that another user is both using the file and has locked the file. You can still make changes to this file even if another user has locked it, but you cannot submit them until the lock is removed.
•	Locked by You
	This indicates that you have locked the file. You will often see this icon in conjunction with the ✓ icon, indicating that you have both locked and checked out the file. Other users can make changes to this file even if you have locked it.

Icon Description

Checked Out to Other User

This indicates that the file is currently checked out by another user. You will often see this icon in conjunction with the icon, indicating that another user is both using the file and has locked the file.

Out of Date

This indicates that the file is not current (i.e., the local copy of the file is older than the source control copy). This might happen, for example, if another user checks out the file, makes changes to it, and submits it to source control. If this occurs, you can check the file out or get the latest version of the file from source control.

Bind Detection, Disabling Providers, and Unbinding Providers—Perforce Helix Core

Flare has options for bind detection, disabling providers, and unbinding providers. Although these are separate features, they are all somewhat related. This information is especially important if you are using an external tool to bind and manage your source control tasks.

Bind Detection

Flare's bind detection settings are found on the Source Control tab of the Options dialog.

Options	
General Interface	✓ Automatically check file out from source control when saving file changes Lock files when automatically checking out (files cannot be checked in by other users) Show prompt to add auto-created files to source control
Source Control Prox server XML Editor	☐ Enable background status checks Update status every 1 → minutes 0 → seconds ☐ Do not prompt to get latest when opening source control bound projects
Project Analysis	 ✓ Prompt to check in files when closing source control bound projects ☐ Enforce TFS comment policy
Auto Suggestion Spelling	Bind Detection ☐ Team Foundation Server ☐ Subversion ☐ Perforce Helix Core ☑ Git
Index & Concepts Keyboard Shortcuts	✓ Use Git executable for network functions C:\Program Files\Git\bin\git.exe
Build Review	MadCap Central Transfer Protocol HTTPS SSH
Plugins Services	

Bind detection scans your project when you load it to see if the project has been previously bound to source control. If a binding is detected, you then have the option of applying the binding and committing the project to source control. Depending on the provider you are using, Flare may search the file system and its artifacts, as well as contact and query servers, to find potential source control bindings.

When you open a Flare project that hasn't been bound to source control before, the bind detection option is disabled for Perforce Helix Core, Subversion, and Team Foundation Server. It is enabled by default for Git and MadCap Central (which uses Git). If you bind a project to source control using the Flare interface, the option is then automatically enabled.

- NOTE You can use bind detection as an alternative to importing a Flare project. If you have received a Flare project file (e.g., by copying it from a server, by opening it from a network location), you can simply open the file and Flare will search for and apply existing source control bindings.
- NOTE Source control providers are scanned in the following order:
 - 1. Git
 - 2. Subversion
 - 3. Perforce Helix Core
- ✓ TIP Detecting source control bindings may take a considerable amount of time. It is recommended that you select only the source control providers that you use to speed up the detection process.

Disabling Providers

By default, when a project is bound to source control, the provider (Git, Perforce Helix Core, Subversion, or Team Foundation Server) is enabled. This means that the source control interface elements in Flare are visible, and you can use them to perform various tasks (e.g., commits, synchronize changes).

Disabling a provider means that the source control interface elements are no longer shown. This does not mean you cannot use source control. As long as the provider is still *bound* to the project, you can perform source control tasks in a third-party tool outside of Flare.

For more details and steps, see "Disabling a Perforce Helix Core Provider" on page 47.

Unbinding Providers

When you unbind a provider, it means you are removing the connection altogether between the Flare project and the local repository.

You can unbind a provider via the Project Properties dialog or the Settings view in the Source Control Explorer. Click the **Unbind Provider** button.

For more details and steps, See "Unbinding a Perforce Helix Core Provider" on page 63.

CHAPTER 3

Process for Perforce Helix Core

Certain tasks must be completed in order when using this feature.

This chapter discusses the following:

Binding a Project to Perforce Helix Core	. 15
Importing From Perforce Helix Core	21
Getting the Latest Version of Source Control Files	. 23
Checking Out Source Control Files	.27
Submitting Source Control Files	.29
Merging Source Control Files	.32

Binding a Project to Perforce Helix Core

Use the following steps if you have already created a Flare project and want to bind ("connect") it to Perforce Helix Core. You can also automatically detect existing source control bindings if your project has been previously connected to Helix Core.

NOTE The following steps show how to bind a project using the Flare interface. It is also possible to bind a project outside of Flare (e.g., using Git Bash). If you decide to do this, you should be aware of some additional aspects of source control, such as bind detection and disabling providers.

How to Bind a Project Using the Project **Properties Dialog**

- 1. Open the project.
- 2. Select Project > Project Properties. The Project Properties dialog opens.
- 3. Select the Source Control tab.
- 4. Click **Bind Project**. The Bind Project dialog opens.
- 5. From the drop-down, select Perforce Helix Core.
- 6. In the Server field, enter the server address.
- 7. Next to the **User** field, click
- 8. Select a user and click **OK**. (Users are set up separately in Perforce Helix Core.)
- 9. From the Type drop-down, select whether you want to bind to a stream or a depot. A depot contains multiple streams.

IF BINDING TO A STREAM

- a. Next to the Stream field, click New.
 - If the Log In dialog opens, complete the **User name** and **Password** fields and click **OK**. The New Stream dialog opens.
- b. From the **Stream Type** drop-down, select the type of stream you want to use. Most streams are mainline streams.
- c. Next to the Streams Depot field, click Browse.
 - The Browse Depots dialog opens.
- d. Select a depot. This is essentially a folder or directory in Perforce Helix Core that contains multiple streams, one of which will be your Flare files.
- e. Click OK.
- f. (Optional) In the New Stream dialog, you can complete any of the other fields as necessary. For information about these fields, please refer to the documentation provided with Perforce Helix Core.
- g. Click OK.

IF BINDING TO A DEPOT

a. Next to the **Depot** field, click **New**, or select an existing depot using the drop-down arrow.

If you clicked **New**, the New Depot dialog opens.

- b. In the Name field, enter a name for the depot.
- c. (Optional) In the **Description** field, enter a description for the depot.
- d. Click OK.
- e. Next to the **Path** field, click

If the Log In dialog opens, complete the **User name** and **Password** fields and click **OK**. The Browse Source Control Folders dialog opens.

- f. Select the location where you want to bind the project.
- g. Click OK.
- 10. (Optional) In the Comment field, you can enter any internal comments.
- 11. (Optional) If you want the files in the project to be checked out when you are finished, click **Keep files checked out**.
- 12. In the Bind Project dialog, click **OK**.
- 13. If the Log In dialog opens, complete the **User name** and **Password** fields and click **OK**. Copies of the Flare files are created and added to the folder you specified.
- 14. In the Project Properties dialog, click **OK**. The project is connected to Perforce Helix Core, and you can now submit files and check them out as necessary.

How to Bind a Project Using the Explorer

- 1. Open the project.
- 2. Select View > Source Control Explorer. The Source Control Explorer opens.
- 3. From the drop-down or the Home pane, select **Settings**. The Settings pane opens.
- 4. Click **Bind**. The Bind Project dialog opens.
- 5. From the drop-down, select **Perforce Helix Core**.
- 6. In the **Server** field, enter the server address.
- 7. Next to the **User** field, click
- 8. Select a user and click **OK**. (Users are set up separately in Perforce Helix Core.)
- 9. From the **Type** drop-down, select whether you want to bind to a stream or a depot. A depot contains multiple streams.

IF BINDING TO A STREAM

- a. Next to the Stream field, click New.
 - If the Log In dialog opens, complete the **User name** and **Password** fields and click **OK**. The New Stream dialog opens.
- b. From the **Stream Type** drop-down, select the type of stream you want to use. Most streams are mainline streams.
- c. Next to the Streams Depot field, click Browse.
 - The Browse Depots dialog opens.
- d. Select a depot. This is essentially a folder or directory in Perforce Helix Core that contains multiple streams, one of which will be your Flare files.
- e. Click OK.
- f. (Optional) In the New Stream dialog, you can complete any of the other fields as necessary. For information about these fields, please refer to the documentation provided with Perforce Helix Core.
- a. Click OK.

IF BINDING TO A DEPOT

a. Next to the **Depot** field, click **New**, or select an existing depot using the drop-down arrow.

If you clicked **New**, the New Depot dialog opens.

- b. In the Name field, enter a name for the depot.
- c. (Optional) In the **Description** field, enter a description for the depot.
- d. Click OK.
- e. Next to the Path field, click

If the Log In dialog opens, complete the **User name** and **Password** fields and click **OK**. The Browse Source Control Folders dialog opens.

- f. Select the location where you want to bind the project.
- g. Click OK.
- 10. (Optional) In the Comment field, you can enter any internal comments.
- 11. (Optional) If you want the files in the project to be checked out when you are finished, click **Keep files checked out**.
- 12. In the Bind Project dialog, click **OK**.
- 13. If the Log In dialog opens, complete the **User name** and **Password** fields and click **OK**. Copies of the Flare files are created and added to the folder you specified. The project is connected to Helix Core, and you can now submit files and check them out as necessary.

What's Noteworthy?

✓ TIP If you are having difficulty binding your project, try binding to a brand new directory in your source control provider. You should also ensure that the directory on your local machine (and its parent directories) is not already mapped to source control, as this may cause issues with binding.

NOTE You can also bind a new Flare project to source control while creating it.

NOTE If you want to publish your output to source control, you must create a bind destination.

I Importing From Perforce Helix Core

This chapter focuses on importing a Flare project from source control. You might use this method, for example, if you are working on a multi-author project and another member of the team has placed the Flare project in Perforce Helix Core.

How to Import a Project From Perforce Helix Core

- 1. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select File > New Project > Import Project.
 - Source Control Explorer From the View ribbon, open the Source Control Explorer. From the drop-down, select the Home pane. Click Import Project.

The Import Project from Source Control Wizard dialog opens.

- 2. From the drop-down, select Perforce Helix Core.
- 3. In the Server field, enter the server address.
- 4. Next to the **User** field, click
- 5. Select a user and click **OK**. (Users are set up separately in Perforce Helix Core.)
- 6. Next to the Location field, click Browse. The Browse Depots and Streams dialog opens.
- 7. Select a depot or stream (i.e., the name of your Flare project).
- 8. Click OK.
- 9. Click Next.
- 10. Next to the **Project file** field, click **Browse**. The Browse Source Control Files dialog opens. (You may need to log in with your user name and password.)
- 11. Find and click on the Flare project file (FLPRJ) that you want to import. (You may need to log in with your user name and password.)
- 12. Click OK.
- 13. Click Next.

- 14. In the **Project name** field, the name of the project being imported is displayed. It is recommended that you leave the name as it is, especially if you are working with other authors on the project. However, you can enter a different project name if you want.
- 15. In the **Project folder** field, either accept the default location for the new project or click to browse for and select a folder.
- 16. Click Finish. The project is imported and loaded into Flare.
- NOTE When a project is dual bound to Central and a non-Git third-party provider, keep the following in mind if you (i.e., the second user) want to access this setup. After importing the project from Perforce Helix Core, Subversion, or Team Foundation Server, you will have to re-bind the project to Central. In Flare's MadCap Central window pane, click to upload (or bind) the project to Central. In the Bind Project dialog, it is important to enter the exact name of the project as it currently exists on Central. When you click **OK**, a message displays asking if you want to bind to the existing project. Select **Yes**. This re-establishes the existing Flare/Central connection; note that it does not create a new binding.
- NOTE If you want to import a project from source control, you can alternatively open the project file from another location (e.g., a server location), and then use Flare's bind detection functionality to automatically apply available source control bindings to the project.

I Getting the Latest Version of Source Control Files

After you bind a Flare project to a source control application, you can get the latest version of any of the source control files. When you do this, you are copying the most current files stored in the source control application to your local Flare project without necessarily checking out the files. This means that the "Read Only" designation will remain associated with the files until you check them out.

Following are steps for getting the latest version of all files in a project automatically, as well as steps for getting the latest version of files manually.

Automatic Get

You might use this option if you are working with a team of authors and want to make sure that you include the latest changes from other writers in the output (without having to manually get those files).

With this option:

- You will not be prompted before the "get" is performed.
- Flare will not get the latest copy of the files in the Targets folder, because that would conflict with the generation of the output.
- Conflicts with files will not cause local files to be overwritten. Therefore, if your local files are
 writable or already checked out, those files will be kept, rather than overwritten with the
 source control files.

How to Get the Latest Version of Source Control Files Automatically

- 1. Open the target.
- 2. In the Target Editor, select the **General** tab.
- 3. Select the check box labeled **Automatically get latest version of all files before generating the target**.
- 4. Click to save your work.
- 5. Build the target.

Manual Get

You can manually get the latest version of all of the files in the Flare project or specific files only.

How to Get the Latest Version of Source Control Files Manually

- 1. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Get Latest Version (for selected files) or Source Control
 > Get Latest Version All (for all files in the project).
 - Right-Click If you have the Content Explorer, Project Organizer, Pending Changes window pane, or File List open, right-click the file you want to get and select Source Control > Get Latest Version.
 - Source Control Explorer With the Pending Changes pane open, right-click the file you want to update and select Get Latest Version.
- 2. If the local and server files are the same, a message tells you so. Click OK.

If the local file is different from the file on the server, the Resolve Conflicts dialog opens. If you want to accept all of the differences between the local and server files, thus merging them, click **Auto Merge All**. If you want to review the differences in the files side by side and resolve each conflict, click **Resolve**

If the local file is different from the file on the server, the Resolve Conflicts dialog opens. If you want to accept all of the differences between the local and server files, thus merging them, click **Auto Merge All**. If you want to review the differences in the files side by side and resolve each conflict, click **Resolve** For more information about merging files and resolving conflicts, see "Merging Source Control Files" on page 32.

What's Noteworthy?

NOTE By default, when you open a project that is bound to source control, a message automatically asks if you want to get the latest version of files. However, you can disable this prompt in the Source Control tab of the Options dialog (File > Options). See "Disabling the Get Latest Prompt for Source Control" on page 46.

NOTE If you update your read-only files with read-only files and you do not perform a check out, the files will appear to be checked in without actually updating the server-side version.

Checking Out Source Control Files

When you need to work on any of the Flare project files, you can check them out. Checking out files means to copy the latest source control files to your local Flare project and remove the "Read Only" designation from them so that you can edit the files. A red check mark is displayed next to each file that is checked out.

You can check files out automatically or manually.

How to Check Out Files From Source Control Automatically

- 1. Select **File > Options**. The Options dialog opens.
- 2. Select the **Source Control** tab.

NOTE This tab will not be visible if your project is not yet bound to source control. See "Binding a Project to Perforce Helix Core" on page 15.

- 3. Click the check box Automatically check file out from source control when saving file changes. A check mark in the box indicates that the feature is enabled.
- 4. (Optional) If you want files that are automatically checked out to be locked as well, select Lock files when automatically checking out.

Locking files means that other users cannot submit those same files when you have them checked out. You might use this feature to prevent conflicting changes from occurring and having to merge files as a result.

5. Click OK.

Whenever you open a file that is not checked out, make changes, and save, not only will your changes be saved but the file will automatically be checked out to you.

How to Check Out Files From Source Control Manually

- 1. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Check Out (for selected files) or Source Control > Check Out All (for all files in the project).
 - Right-Click If you have the Content Explorer, Project Organizer, Pending Changes window pane, or File List open, right-click the file you want to check out and select Source Control > Check Out (for selected files) or Source Control > Project > Check Out All (for all files in the project).

The Check Out dialog opens. The selected files are listed with check boxes next to them.

- 2. Make sure to click the check box next to each file you want to check in so that it contains a check mark.
- 3. (Optional) If you want the files to be locked as well, select Lock files.
 Locking files means that other users cannot submit those same files when you have them checked out. You might use this feature to prevent conflicting changes from occurring and having to merge files as a result.
- 4. Click Check Out.

Submitting Source Control Files

When you are finished editing files, you can submit them to source control. Submitting a file overwrites the old copy of the file in the source control database with the new one from your local machine. So even if others will not be working on that file, it is a good idea to periodically submit files so that you have a backup in source control.

How to Submit Files to Source Control

- 1. Do one of the following, depending on the part of the user interface you are using:
 - Pending Changes Window Pane From the Source Control ribbon, open the Pending Changes window pane. Select the files in the window pane that you want to submit, and in the local toolbar click submit...
 - Ribbon Select Source Control > Submit (for selected files) or Source Control > Submit All (for all files in the project).
 - Right-Click If you have the Content Explorer, Project Organizer, Pending Changes window pane, or File List open, right-click the file you want to submit and select Source Control > Submit (for selected files) or Source Control > Project > Submit All (for all files in the project).

The Submit dialog opens. The selected files are listed with check boxes next to them.

- 2. (Optional) In the **Comment** field, enter an optional comment tied to the submit. This enables you to keep an audit trail for a file. The comment can then be viewed from the History dialog, which can be accessed from the Source Control Explorer, the Source Control ribbon, the File menu, or the Source Control button
- 3. (Optional) If you want to see all files with pending changes (rather than only those you selected), click .
- 4. Make sure to click the check box next to each file you want to check in so that it contains a check mark.
- 5. If you want to keep the files checked out of source control, select **Keep Checked Out**. Doing this will overwrite the source control copies of the files so that they have the latest changes, but it lets you continue working on the files. This is a useful option if you are the only author working on the files in question.

6. Click Submit.

If no other users have also made changes to the file and submitted it while you were working on it, your version of the file is submitted.

However, if that is not the case, the Resolve Version Conflict dialog opens to let you know that another user has already submitted the file with changes. You can merge the files automatically if there are no conflicting changes (i.e., changes do not occur in the same location in the file). If there are conflicting changes, you can use the Merge Changes dialog to determine how changes are merged. See "Merging Source Control Files" on page 32.

How to Submit Files to Source Control Using the **Explorer**

- 1. Select View > Source Control Explorer. The Source Control Explorer opens.
- 2. From the drop-down or the Home pane, select Pending Changes.

The Pending Changes pane opens. Files that will be committed are listed under Included Changes, and files that will not be committed are listed under Excluded Changes. You can identify edited files because [modified] is displayed next to the file name.



NOTE When you check out a file in source control, you may sometimes see a SKL file alongside the XLF and original files. This skeleton file is a placeholder file. Be sure to submit all three associated files together. Submitting just the SKL file may result in errors.

- 3. (Optional) In the Comment field, enter an optional comment tied to the submit. This enables you to keep an audit trail for a file. The comment can then be viewed from the History dialog, which can be accessed from the Source Control Explorer, the Source Control ribbon, the File menu, or the Source Control button ...
- 4. (Optional) If you want to select the files or folders that you include in the submit, right-click a file or folder and select one of the following options from the context menu.
 - **Exclude** Excludes the selected file from the submit
 - Exclude Unselected Excludes all unselected files from the submit
 - Include Includes the selected file in the submit
 - Include Unselected Includes all unselected files in the submit
- 5. Click **Submit Included** to submit all of the files in the Included Changes list. The Messages pane opens and displays a list of files that were submitted.

If no other users have also made changes to the file and submitted it while you were working on it, your version of the file is submitted.

However, if that is not the case, the Resolve Version Conflict dialog opens to let you know that another user has already submitted the file with changes. You can merge the files automatically if there are no conflicting changes (i.e., changes do not occur in the same location in the file). If there are conflicting changes, you can use the Merge Changes dialog to determine how changes are merged. See "Merging Source Control Files" on the next page.

Merging Source Control Files

There may be times when you need to merge changes from different authors when checking in a file. The merge occurs automatically if there are no conflicting changes (i.e., changes do not occur in the same location in the file). If there are conflicting changes, a dialog opens, allowing you to determine how changes are merged.

If you selected the option to use the merge tool, the Merge Changes dialog opens. Use this dialog to view and select changes. You can take actions in the following ways.

How to Merge Source Control Files

- 1. Go through the process of getting the latest version of files from source control or submitting files. See "Getting the Latest Version of Source Control Files" on page 23 and "Submitting Source Control Files" on page 29. If your local copy of the file is different from the server copy (e.g., another author has already submitted the same file), the Resolve Conflicts dialog opens.
- 2. Click **Auto Merge All**. If changes from the other author do not conflict with your changes, this will merge all changes. A message lets you know that a backup of your local copy has been made. This lets you restore that file if you do not want to keep the merged version. You do not need to complete the rest of the steps below.
 - However, if your changes conflict with those from another author, a message displays to tell you. In this case, continue with the next step.
- 3. Click **OK** on the conflict message.
- 4. In the Resolve Conflicts dialog click **Resolve**. The Resolve Version Conflict dialog opens. From this dialog, you can choose from the following options.
 - Merge changes for me Automatically merges changes within the same file that are not part of the same element. If changes have been made to the same element (e.g., the same tag or <h1> tag), Flare will display a prompt to merge the changes using the merge tool.
 - Merge changes in merge tool Opens a merging interface, which lets you see exactly what changes were made and choose which to keep.
 - Undo my local changes Automatically removes your changes and keeps changes from other authors.

- Discard external changes Automatically removes changes from other authors and keeps your changes.
- 5. If you selected the option to use the merge tool, the Merge Changes dialog opens. Use this dialog to view and select changes. You can take actions in the following ways.
 - Click a change You can click a change on either the remote or local side. This lets you select a particular change. Use the key at the top of the merge changes dialog, as well as the color coding on the local and server sides, to determine if a change has been added (new), deleted, changed, or moved.
 - When you select a change, the change you selected will display with a solid colored background, and the conflicting change will display with a striped background. If you select the other change, the background shading will switch.
 - Type content If you want to use your changes as well as those from another author, and even tweak the paragraph a bit more, you can click in the area at the bottom of the dialog and simply type content.
 - Previous/next conflict When you are finished resolving the first conflict, you can use the "Previous Conflict" and "Next Conflict" buttons at the bottom of the dialog to work on other conflicts in the file.
 - NOTE If you selected "Merge as Text" in the local toolbar and are working in the code, you can click on text with a hatched background to keep the change in it. After you click on text with a hatched background, the hatched lines are removed, leaving a solid color.
- 6. After all conflicts have been resolved, a message lets you know that a backup of your local copy has been made. This lets you restore that file if you do not want to keep the merged version. Click **OK**.

☆ EXAMPLE — Auto Merging


Let's say two authors —Bob and Jill—are working on the same project, using source control to manage the files.

Bob checks out the "FAQs" topic and starts making changes to it.

Jill also checks out the "FAQs" topic and makes some changes to it. Jill's changes are in a different location in the topic than Bob's changes; there are no conflicts. She finishes before Bob and submits the file to source control.

Bob finishes his changes and tries to submit the file. Before the file can be submitted, Bob is prompted with a dialog, indicating that changes from another author have already been submitted.

Bob selects Auto Merge All. The changes from Bob and Jill are now both shown in the merged topic.






★ EXAMPLE — Conflicting Changes

Let's say two authors—Bob and Jill—are working on the same project, using source control to manage the files.

Bob checks out the "FAQs" topic and starts making changes to it.


Jill also checks out the "FAQs" topic and makes some changes to it. Jill's changes are in the same paragraph in the topic as Bob's changes; thus, there is a conflict. She finishes before Bob and commits the file to source control.

Bob finishes his changes and tries to submit the file. Before the file can be submitted, Bob is prompted with a dialog, indicating that changes from another author have already been submitted.







Bob selects **Auto Merge All**. However, he receives another message, stating that his changes conflict with those of Jill.



Bob clicks **OK**. Then in the Resolve Conflicts dialog he clicks **Resolve**. This opens the Resolve Version Conflict dialog. From this dialog, Bob can choose from a few different options.






CHAPTER 3 37




So what action can Bob take at this point for merging the file changes?

Bob can right-click on the icon next to the change on either the local or server side. This displays a context menu, which lets Bob either keep or ignore a particular change.



CHAPTER 3 38






Another way of accomplishing the same thing is to left-click on an icon. When you do this, the change from one side is kept and the change from the other side is ignored. If you left-click the icon again, the results are toggled; the first change is ignored and the other is kept.

What if Bob wants to use his changes as well as Jill's, and possibly tweak the paragraph a bit more? He can click in the area at the bottom of the dialog and simply type content.

CHAPTER 3 39



When he is finished resolving the first conflict, Bob can use the "Previous Conflict" and "Next Conflict" buttons at the bottom of the dialog to work on other conflicts in the file.



After all conflicts have been resolved, Bob clicks OK. The merged topic is now submitted to source control.

40 CHAPTER 3

CHAPTER 4

Other Activities for Perforce Helix Core

In addition to the many features already covered in this guide, there are many more tasks related to source control that you can perform in Flare.

This chapter discusses the following:

Adding Files to Source Control	43
Deleting Source Control Files	45
Disabling the Get Latest Prompt for Source Control	46
Disabling a Perforce Helix Core Provider	47
Disconnecting From Source Control	49
Enabling Source Control Status Checks	51
Locking a File	52
Publishing to Source Control	53
Reverting a Checkout of Source Control Files	54
Rolling Back to an Earlier Version of a File	55
Setting Color Options for Project File Differences	61
Unbinding a Perforce Helix Core Provider	63
Undeleting Source Control Files	65
Unlocking a File	66
Viewing Differences in Source Control Files	67

Viewing Files That are Checked Out	70
Viewing the History of Source Control Files	76

Adding Files to Source Control

When working in a project that is connected to source control, there may be occasions when you have files in your local copy of the project that are not yet part of the source control copy. For example, when you add a new topic in your local copy of the project, that file will not be included in the source control copy of the project until you add it.

How to Add Files to Source Control


- 1. Do one of the following, depending on the part of the user interface you are using:
 - RibbonSelect Source Control > Add.
 - Right-Click If you have the Content Explorer, Project Organizer, Pending Changes window pane, or File List open, right-click the file you want to add and select Source Control > Add.

The Submit dialog opens. The selected files are listed with check boxes next to them.

- 2. (Optional) Enter an optional comment tied to the submit. This enables you to keep an audit trail for a file. The comment can then be viewed from the History dialog, which can be accessed from the Source Control Explorer, the Source Control ribbon, the File menu, or the Source Control button
- 3. (Optional) If you want to see all files with pending changes (rather than only those you selected), click .
- 4. Make sure to click the check box next to each file you want to check in so that it contains a check mark.
- 5. If you want to automatically check the files out of source control, select Keep Checked Out.
- 6. Click Submit.

How to Add Files to Source Control Using the Explorer

- 1. Select View > Source Control Explorer. The Source Control Explorer opens.
- 2. From the drop-down or the Home pane, select Pending Changes.
 - The Pending Changes pane opens. Files that will be submitted are listed under **Included Changes**, and files that will not be submitted are listed under **Excluded Changes**. You can identify newly added files because they say **[add]** next to the file name.
- 3. (Optional) Enter an optional comment tied to the submit. This enables you to keep an audit trail for a file. The comment can then be viewed from the History dialog, which can be accessed from the Source Control Explorer, the Source Control ribbon, the File menu, or the Source Control button
- 4. (Optional) If you want to select the files or folders that you include in the submit, right-click a file or folder and select one of the following options from the context menu.
 - **Exclude** Excludes the selected file from the submit
 - Exclude Unselected Excludes all unselected files from the submit
 - Include Includes the selected file in the submit
 - Include Unselected Includes all unselected files in the submit
- 5. Click **Submit Included** to submit all of the files in the Included Changes list. The Messages pane opens and displays a list of files that were submitted.



Deleting Source Control Files

You can delete a topic or file that is bound to source control. This also removes the file from Perforce Helix Core.

How to Delete a File

- 1. In one of the window panes (e.g., Content Explorer, File List, Project Organizer, Pending Changes window pane), select the relevant file(s).
- 2. On your keyboard press DELETE.
- 3. The Delete dialog opens. Select the bound files you want to delete.
- 4. Click **Delete**. The files are removed from your project and from the source control repository.

Disabling the Get Latest Prompt for Source Control

By default, when you open a project that is bound to source control, a message automatically asks if you want to get the latest version of files. However, you can disable this prompt in the Source Control tab of the Options dialog (File > Options). Therefore, in the future when you open the project you will no longer see the message, and the project will open without replacing any local files with the latest ones from source control.

How to Disable the Get Latest Prompt for Source Control

- 1. Select File > Options. The Options dialog opens.
- 2. Select the **Source Control** tab.

NOTE This tab will not be visible if your project is not yet bound to source control. See "Binding a Project to Perforce Helix Core" on page 15.

- 3. Click the check box Do not prompt to get latest when opening source control bound projects.
- 4. Click OK.

Disabling a Perforce Helix Core Provider

By default, when a project is bound to source control, the provider (Git, Perforce Helix Core, Subversion, or Team Foundation Server) is enabled. This means that the source control interface elements in Flare are visible, and you can use them to perform various tasks (e.g., commits, synchronize changes).

Disabling a provider means that the source control interface elements are no longer shown. This does not mean you cannot use source control. As long as the provider is still *bound* to the project, you can perform source control tasks in a third-party tool outside of Flare.

How to Disable a Provider

Use this method if you want to disable a provider in just one project, rather than many projects.

- 1. Do one of the following, depending on the part of the user interface you are using:
 - Project Properties Select Project > Project Properties.
 - Source Control Explorer Select View > Source Control Explorer. Then, in the window pane, click Settings.
- 2. Click **Enabled** to remove the check mark.
- 3. If you used the Project Properties dialog, click **OK**.
- NOTE If you disable a Git provider, the local repository will continue to track your changes in case you later decide to enable the provider once again.

 If you disable one of the other providers (Perforce Helix Core, Subversion, Team Foundation)

If you disable one of the other providers (Perforce Helix Core, Subversion, Team Foundation Server), your changes after that point will not be tracked. Therefore, if you later enable the provider again, it will not have recorded any changes made since the time that you disabled it.

NOTE When you disable a provider, that information is written to the registry on your computer.

- NOTE If you disable a provider, but then perform one of the following actions in the Flare interface, the provider will automatically become enabled once again.
 - Bind an existing project
 - Bind a new project
 - Bind a project to Central (either as secondary or primary provider)
 - Import a project from source control
 - Import a project from Central
- NOTE Having a provider enabled in Flare does not interfere with your workflow if you are performing source control actions exclusively outside of Flare. Even if a provider is enabled in the project and the source control user interface elements are visible, this does not mean Flare is automatically performing any source control actions with your files. It simply means Flare is recognizing the binding, so it reflects your activities (e.g., the Pending Changes window is populated when you make edits in topics). However, if you prefer not to see any of this in Flare, you can disable the provider.

Disconnecting From Source Control

There may be times that you need to disconnect from source control to work offline. You can disconnect from Perforce Helix Core and reconnect at any time.

Disconnecting from source control is beneficial because it lets you modify files when you would otherwise not have access to the source control system (e.g., you are out of the office with your laptop or you do not want to access source control over VPN). It also provides a fallback offline status in the event that the network is disconnected while you are working, so you are able to continue working on the files you have checked out until the network connection is restored.

How to Disconnect From Perforce Helix Core

When you want to work offline, you can disconnect from source control.

- 1. Check out the files you will need to work on while disconnected. See "Checking Out Source Control Files" on page 27.
- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Disconnect.
 - Right-Click If you have the Content Explorer, Project Organizer, Pending Changes window pane, or File List open, right-click on any file and select Source Control > Project > Disconnect.
- 3. A confirmation dialog appears. Click Yes. You will be disconnected from source control.
- NOTE When you disconnect from source control, you are not able to see the source control status of files or access source control functions.
- NOTE If you attempt to modify a file that is not checked out, you will receive an error when you try to save the file. To avoid this, be sure you have all necessary files checked out before disconnecting from source control.

NOTE If you make a change to a file's properties (e.g., delete, rename) while disconnected from source control, your changes may not be preserved when you reconnect to the network. To prevent errors, it is recommended that you do not make these kinds of changes until you reconnect to source control.

How to Reconnect to Perforce Helix Core

When you are finished working offline, you can reconnect to source control.

- 1. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Reconnect.
 - Right-Click If you have the Content Explorer, Project Organizer, Pending Changes window pane, or File List open, right-click on any file and select Source Control > Project > Reconnect.
- 2. Submit the files you previously checked out. See "Submitting Source Control Files" on page 29.

What's Noteworthy?

NOTE Your current network connection status is indicated in the lower right corner of the Flare interface. If you are connected you will see Connected; if you are disconnected you will see Disconnected.

I Enabling Source Control Status Checks

If you are using source control integration in Flare, you can check for frequent status changes automatically. You can specify the number of minutes and seconds when you want Flare to ping the source control repository and get status changes for files that have been checked out, submitted, moved, deleted, etc. The upside of this feature is that you can ensure that the source control status information is always up to date. The downside is that you may experience slower performance due to this constant communication over the network.

How to Enable Source Control Status Checks

how to enable source control status checks

- 1. Select **File > Options**. The Options dialog opens.
- 2. Select the Source Control tab.
 - NOTE This tab will not be visible if your project is not yet bound to source control. See "Binding a Project to Perforce Helix Core" on page 15.
- 3. Click the check box **Enable background status checks**. A check mark in the box indicates that the feature is enabled.
- 4. Enter the number of minutes and or seconds between each status update.
- 5. Click OK.
- NOTE If you elect to disable this feature (disabled is the default setting), you can manually check for status updates by refreshing the Pending Changes window pane or Source Control Explorer. See "Viewing Files That are Checked Out" on page 70.

Locking a File

When you are working, you may want to lock the files you have modified. Locking a file does not prevent other users from modifying the file. However, no one else can commit a file that you have locked until you unlock the file. If your project is bound to Subversion, you can steal a lock from another user if you need to commit a locked file while they are working on it. Likewise, another user can steal a lock on a file you have locked. You will see this option if your project is bound to Perforce Helix Core or Subversion.

How to Lock a File

1. In one of the window panes (e.g., Content Explorer, Source Control Explorer, File List, Project Organizer, Pending Changes window pane), select the relevant file(s).

OR

Open a file.

- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Lock.
 - Right-Click If you have the Content Explorer, Project Organizer, Pending Changes window pane, or File List open, right-click the files you want to lock and select Source Control > Lock.
 - Source Control Explorer Right-click the files you want to lock and select Lock.

The Lock dialog opens. The selected files are listed with check boxes next to them.

- 3. Make sure to select the check box next to each file you want to lock so it contains a check mark.
- 4. Click Lock.



Publishing to Source Control

You can use Flare to directly publish your output to source control, rather than having to upload it to source control separately. Publishing your output to source control is beneficial because it you can keep previous versions of your output in source control and access them if necessary.

For more information about creating publishing destinations, see the online Help.

How to Publish Output to Source Control

1. Create a new source control publishing destination, or select an existing source control publishing destination.



NOTE When creating a new source control destination, be sure to select **Source Control** from the **Type** drop-down.

- 2. Assign the publishing destination to the target you want to publish.
- 3. Build and publish your output. Your output files will be published to the source control location you specified in the destination.

Reverting a Checkout of Source Control Files

If you have files checked out from source control but do not want them checked out anymore, you can use the "Revert" option instead of submitting the files. While submitting the file would save your changes to source control, reverting a checkout returns the files to their previously submitted state and does not submit any of your changes to source control.

How to Revert a Source Control File

- 1. In one of the window panes (e.g., Content Explorer, Source Control Explorer, File List, Project Organizer, Pending Changes window pane), select the relevant file(s).
- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Revert (for selected files) or Revert All (for all files in the project).
 - Right-Click If you have the Content Explorer, Project Organizer or File List open, right-click the files you want to revert and select Source Control > Revert (for selected files) or Source Control > Project > Revert All (for all files).

The Undo Check Out dialog opens. The selected files are listed.

- 3. (Optional) If you want to see all files with pending changes (rather than only those you selected), click .
- 4. Make sure to click the check box next to each file you want to check in so that it contains a check mark.
- 5. Click Undo Check Out.

Rolling Back to an Earlier Version of a File

One of the benefits of Flare's integrated source control is that you can view the history and differences for a particular file. You can view code and content differences between two source control versions of the same file. This is useful if you need to roll back to an earlier version of a file.

See "Viewing the History of Source Control Files" on page 76 and "Viewing Differences in Source Control Files" on page 67.



EXAMPLE You have been working on a particular topic for a few days. Each day you check out the latest version of that topic file from source control, make your changes, and submit the file back to source control at the end of the day. At a certain point, you determine that you need to "roll back" to an earlier version of the file, using it to replace the latest version. Therefore, you use this feature to view the highlighted differences between the current version and an older version of the file. Once you have identified the older version that you want to use, you can perform a "get" of that version.

How to Roll Back to an Earlier Version of a File

1. In one of the window panes (e.g., Content Explorer, Source Control Explorer, File List, Project Organizer, Pending Changes window pane), select the relevant file(s).

OR

Open a file.


- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > View History.
 - Right-Click If you have the Content Explorer, Project Organizer, Pending Changes window pane, or File List open, right-click the file you want to roll back and select Source Control > View History.
 - Source Control Explorer With the Pending Changes pane open, right-click the file you
 want to roll back and select View History.

The History dialog opens.


3. (Optional) View the differences between two versions of the file. This may help you decide which version of the file you want to retrieve. (Another way is to look at the dates for each version in the History dialog.)


To view the differences, follow these steps.

- a. Select the first file version from the list.
- b. Hold the CTRL key and select the second file version from the list.
- c. Click **Show Differences**. The Differences Editor opens to the right, showing content from the backup file on the left and the current version of the file on the right.
- d. In the local toolbar of the Differences Editor, you can click any of the following to make adjustments.
 - Options Click this to open the File Differences dialog, which lets you change the colors used to display content differences between the files.
 - Show WYSIWYG Click this to switch from tag view to WYSIWYG (What You See Is What You Get) view.





■ Ignore Case Click this to ignore changes in case when viewing differences. This option can be used in "text view" only; it is not available in WYSIWYG view.





• Ignore Whitespace Click this to ignore whitespace when viewing differences.





- e. When you are finished viewing the differences, close the window pane.
- 4. In the History dialog, select the version of the file to which you want to roll back.
- 5. Click **Get Selected Version**. That file is downloaded from source control and replaces the local copy of the file in your project.
- 6. In the History dialog, click Close.

Setting Color Options for Project File Differences

If you are using Flare's integrated source control features, you can view differences between files in various ways. One way is to view file differences between a local version of a Flare project and the source control version.

When viewing file differences between a local version of a Flare project and the source control version, you can select color options to display the files. Color coding makes it easier to discern where differences between files occur.

For more information see "Viewing Differences in Source Control Files" on page 67.



EXAMPLE By default the files that are included only in your local copy are displayed as green in the Differences Editor, and the files that are included only in source control are displayed in red. You can use this dialog to change the local-only files to blue and the source control-only files to yellow.

61 CHAPTER 4

How to Set Color Options for Project File Differences

1. In one of the window panes (e.g., Content Explorer, Source Control Explorer, File List, Project Organizer, Pending Changes window pane), select the relevant file(s).

OR

Open a file.

- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Show Differences.
 - Right-Click If you have the Content Explorer, Project Organizer, Source Control Explorer, Pending Changes window pane, or File List open, right-click the file you want to view and select Source Control > Show Differences.

The Differences Editor opens.

- 3. In the local toolbar of the Differences Editor, click **Options**. The File Differences dialog opens.
- 4. Change the text or background color for any of the difference types. To do this, simply click in the appropriate **Text** or **Background** cell and select **Pick Color**. In the Color Picker dialog, choose the new color.

5. Click OK.

Unbinding a Perforce Helix Core Provider

When you unbind a provider, it means you are removing the connection altogether between the Flare project and the local repository.

How to Unbind Using the Project Properties Dialog

- 1. Open the project.
- 2. Select Project > Project Properties.
- 3. Select the Source Control tab.
- 4. Click **Unbind Provider**. (If your project is dual-bound, you will also see a section for the other binding.)
- 5. Click OK.

How to Unbind Using the Source Control Explorer

- 1. Open the project.
- 2. Select View > Source Control Explorer.
- 3. From the drop-down or the Home pane, select Settings. The Settings pane opens.
- 4. Click **Unbind Provider**. (If your project is dual-bound, you will also see a section for the other binding.)
- 5. Click Yes.

What's Noteworthy?

NOTE You can also disable a provider, which retains the binding but hides source control elements from the user interface.

NOTE If you are using a dual-bound setup where you are bound to MadCap Central and a third-party provider, you might decide at some point to move to a single-bound configuration, removing one of the bindings but leaving the other.

Undeleting Source Control Files

If you have a file marked as "Deleted" but then want to add it to source control, you can undelete the file, which then lets you do this. You might encounter this situation if you rename a file and then create a new file with that name, or if you rename a file to the name of a previously deleted file.



NOTE You can only undelete files from Microsoft Team Foundation Server and Perforce Helix Core. When you delete files from other source control providers, they are removed from the source control repository.

How to Undelete a Source Control File

- 1. In one of the window panes (e.g., Content Explorer, Project Organizer, Pending Changes window pane), select the relevant file(s).
- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Undelete.
 - Right-Click If you have the Content Explorer, Project Organizer, or Pending Changes window pane open, right-click the file you want to undelete and select Source Control > Undelete.
- 3. The Undelete dialog opens. Select the files you want to undelete.
- 4. Click OK.

Unlocking a File

If you have locked a file, you should unlock it when you are done modifying it. Other users can modify the file while you have it locked, but they cannot submit a locked file until you unlock it. To help prevent file conflicts and make sure that everyone on your team has the most current version of the file, you should unlock and submit the file when you are finished working on it.

See "Locking a File" on page 52 for more information on locking files.

How to Unlock a File

1. In one of the window panes (e.g., Content Explorer, Source Control Explorer, File List, Project Organizer, Pending Changes window pane), select the relevant file(s).

OR

Open a file.

- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Unlock.
 - Right-Click If you have the Content Explorer, Project Organizer, Pending Changes window pane, or File List open, right-click the files you want to unlock and select Source Control > Unlock.
 - Source Control Explorer Right-click the files you want to unlock and select Unlock.

The Unlock dialog opens. The selected files are listed with check boxes next to them.

- 3. Make sure to click the check box next to each file you want to check in so that it contains a check mark.
- 4. Click Unlock.

Viewing Differences in Source Control **Files**

One of the benefits of Flare's integrated source control is that you can view the history and differences for a particular file.

Ways to View Differences Between Files

You can view differences between files in the following ways:

■ Two Versions of Same Source Control File (History/Roll Back) You can view code and content differences between two source control versions of the same file. This is useful if you need to roll back to an earlier version of a file.



EXAMPLE You have been working on a particular file for a few days. Each day you check out the latest version of that file from source control, make your changes, and check the file back in to source control at the end of the day. At a certain point, you determine that you need to "roll back" to an earlier version of the file, using it to replace the latest version. Therefore, you use this feature to view the highlighted differences between the current version and an older version of the file. Once you have identified the older version that you want to use, you can perform a "get" of that version.

Local Versus Source Control Version of a File You can view code and content differences between the local version of a file and the source control version of that file.



EXAMPLE You check out a procedure topic from source control and then add some lines of text to your local copy of that topic file. You save your changes. Later that day, you want to revisit the new content that you wrote, but you cannot remember exactly which lines of text you added. Therefore, you use this feature to highlight the text differences between your local version of the file and the version stored in the source control application. The new lines of text are highlighted on the side displaying the local version of the file.

67 CHAPTER 4

How to View Differences Between Two Versions of the Same Source Control File

- 1. In one of the window panes (e.g., Content Explorer, Source Control Explorer, File List, Project Organizer, Pending Changes window pane), select the relevant file(s).
- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > View History.
 - Right-Click If you have the Content Explorer, Project Organizer, Source Control Explorer, Pending Changes window pane, or File List open, right-click the file(s) you want to view and select Source Control > View History.

The History dialog opens.

- 3. From the list, select the first file version that you want to compare.
- 4. Hold the CTRL key and select the second file version from the list.
- 5. Select **Show Differences**. The Differences Editor opens.
- 6. (Optional) In the Differences Editor, use the buttons in the local toolbar to customize the information shown in the editor.
- 7. When you are finished viewing the differences, close the window.

How to View Differences Between the Local Version of a File and the Source Control Version

- 1. In one of the window panes (e.g., Content Explorer, Source Control Explorer, File List, Project Organizer, Pending Changes window pane), select the relevant file(s).
- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > Show Differences.
 - Right-Click If you have the Content Explorer, Project Organizer, Source Control Explorer, Pending Changes window pane, or File List open, right-click the file(s) you want to view and select Source Control > Show Differences.

The Differences Editor opens.

- 3. (Optional) In the Differences Editor, use the buttons in the local toolbar to customize the information shown in the editor.
- 4. When you are finished viewing the differences, close the window.

Viewing Files That are Checked Out

You can use the Pending Changes window pane and the Source Control Explorer to view all of the files that you have checked out and need to submit. You can use the File List window pane and Pending Changes window pane to view files that are checked out by other users.

How to View Files That You and Others Have Checked Out—Pending Changes Window Pane

- 1. Select Source Control > Pending Changes.
 - The Pending Changes window pane opens.
- 2. (Optional) You can use the **Filter** field to limit the files that are displayed.
 - All Files Displays all files.
 - Topic Files Displays only the topic (HTM and HTML) files.
 - Template Page Files Displays only the template page (FLMSP) files.
 - Page Layout Files Displays only the page layout (FLPGL) files.
 - Snippet Files Displays only the snippet (FLSNP) files.
 - Micro Content Files Displays only the micro content (FLMCO) files.
 - Stylesheet Files Displays only the stylesheet (CSS) files.
 - Image Files Displays only the image files.
 - Multimedia Files Displays only multimedia (audio, video, and 3D model) files.
 - GIF Files Displays only GIF files.
 - JPEG Files Displays only JPG and JPEG files.
 - PNG Files Displays only PNG files.
 - Flash Movie Files Displays only SWF files.

3. (Optional) You can use the following toggle buttons in the local toolbar to limit the files that are displayed.

Option	Description
2	This filters the Pending Changes window pane to show or not show files that other users have checked out.
	This filters the Pending Changes window pane to show or not show files that are out of date.
	This filters the Pending Changes window pane to show or not show files that have been deleted.
	This filters the Pending Changes window pane to show or not show files that are locked.

- 4. Take note of the **Status** and **User** columns. (You may need to use the scroll bar to view these columns.)
 - Status Displays the status of the file, such as whether you have it checked out. You can
 also see if another user has a file checked out.
 - Checked Out This indicates that the file has been checked out from source control. You can submit the file when you are ready (if you are the user who has checked it out).
 - Pending Add This indicates that you have a file in your project but have not yet
 added it to Perforce Helix Core. This might occur, for example, if you create a new
 topic and do not add the file to source control during the topic creation process. To
 resolve this, simply right-click on the file and select Source Control > Add.
 - Out of Date This indicates that the file is not current (i.e., the local copy of the file is older than the source control copy). This might happen if another user checks out the file, makes changes to it, and checks it back in to source control. If this occurs, you can check the file out or get the latest version of the file from source control.
 - Locked This indicates that a file has been locked by you or another user.

- NOTE You can click the refresh button in the local toolbar to make sure you have the most recent status for each file. Another option is that you can use a feature to automatically ping the source control repository periodically, thus refreshing this information frequently. However, you may experience slower performance with this automatic status update option set. See "Enabling Source Control Status Checks" on page 51.
- User Displays the user name. If you see the name of another user in this column, it means that the file is checked out by that user through source control.

How to View Files That are Checked Out by Others—File List Window Pane

- 1. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select View > File List.
 - Keyboard Shortcut Press CTRL+SHIFT+J.
- 2. (Optional) You can use the **Filter** field to limit the files that are displayed.
 - All Files Displays all files.
 - Topic Files Displays only the topic (HTM and HTML) files.
 - Template Page Files Displays only the template page (FLMSP) files.
 - Page Layout Files Displays only the page layout (FLPGL) files.
 - Snippet Files Displays only the snippet (FLSNP) files.
 - Micro Content Files Displays only the micro content (FLMCO) files.
 - Stylesheet Files Displays only the stylesheet (CSS) files.
 - Image Files Displays only the image files.
 - Multimedia Files Displays only multimedia (audio, video, and 3D model) files.
 - GIF Files Displays only GIF files.
 - JPEG Files Displays only JPG and JPEG files.
 - PNG Files Displays only PNG files.
 - Flash Movie Files Displays only SWF files.

- 3. Take note of the **Status** and **User** columns. (You may need to use the scroll bar to view these columns.)
 - Status Displays the status of the file, such as whether you have it checked out. You can also see if another user has a file checked out.
 - NOTE You can click the refresh button in the local toolbar to make sure you have the most recent status for each file. Another option is that you can use a feature to automatically ping the source control repository periodically, thus refreshing this information frequently. However, you may experience slower performance with this automatic status update option set. See "Enabling Source Control Status Checks" on page 51.
 - User Displays the user name. If you see the name of another user in this column, it means that the file is checked out by that user through source control.

How to View Files That You Have Checked Out— Source Control Explorer


1. Select View > Source Control Explorer.

The Source Control Explorer opens.

2. From the drop-down or the Home pane, select Pending Changes.

The Pending Changes pane opens. Files that you have changed appear in the **Included Changes** or **Excluded Changes** section (depending on whether you are going to include or exclude them in your next submit; see "Submitting Source Control Files" on page 29).

3. Take note of the file's status. The status is written in brackets next to the file name (e.g., edit, add).



Viewing the History of Source Control Files

One of the benefits of Flare's integrated source control is that you can view the history for a particular file, including who submitted the file and when it was submitted. You can also view differences between different versions of the file and roll back to an older version if necessary.

For more information see "Viewing Differences in Source Control Files" on page 67 and "Rolling Back to an Earlier Version of a File" on page 55.

How to View the History of a Source Control File

1. In one of the window panes (e.g., Content Explorer, Source Control Explorer, File List, Project Organizer, Pending Changes window pane), select the relevant file(s).

OR

Open a file.

- 2. Do one of the following, depending on the part of the user interface you are using:
 - Ribbon Select Source Control > View History.
 - Right-Click If you have the Content Explorer, Project Organizer, Source Control Explorer, Pending Changes window pane, or File List open, right-click the file(s) you want to view and select Source Control > View History.Right-Click If you have the Source Control Explorer or File List open, right-click the file(s) you want to view and select Source Control > View History.
- 3. The History dialog opens. The following are explanations of the different parts of this dialog.
 - Version Displays a number for each version of the file. The lower the number, the older the version. The higher the number, the more recent the version.
 - Users Displays the name of the user who has been working on the file.
 - Date Displays the date and time when the action has occurred.
 - Action Displays the action that has taken place for the file (e.g., submit).
 - Comment Displays the comment (if any) associated with the file. A comment can be added to a file when you submit that file to source control. This enables you to maintain an audit trail for the file's history.

- Get Selected Version Performs a "get" of a particular version of a file, thus rolling back to that version of the file. The local version of the file is replaced with the source control version that you selected.
- Show Differences Opens a dialog that lets you view the differences between two versions of a file. If you select one row in the History dialog and view the differences, you will see the content differences between the version that you selected and the version of the file in your local copy of the Flare project. If you select two files in the History dialog (by holding down the CTRL key) and view the differences, you will see the content differences between those two versions of the file.

4. In the History dialog, click Close.

APPENDIX

PDFs

The following PDFs are available for download from the online Help.

I Tutorials

Autonumbers Tutorial

Back-to-Top Button Tutorial

Context-Sensitive Help Tutorial

Custom Toolbar Tutorial

eLearning Tutorial—Basic

eLearning Tutorial—Advanced

Getting Started Tutorial

Image Tooltips Tutorial

Lists Tutorial

Meta Tags Tutorial

Micro Content Tutorial—Basic

Micro Content Tutorial—Advanced

Responsive Output Tutorial

Single-Sourcing Tutorial

Snippet Conditions Tutorial

Styles Tutorials

Tables Tutorial

Word Import Tutorial

APPENDIX 78

I Cheat Sheets

Context-Sensitive Help Cheat Sheet

Folders and Files Cheat Sheet

Learning & Development Cheat Sheet

Lists Cheat Sheet

Micro Content Cheat Sheet

Print-Based Output Cheat Sheet

Search Cheat Sheet

Shortcuts Cheat Sheet

Structure Bars Cheat Sheet

Styles Cheat Sheet

APPENDIX 79

User Guides

Guide

Meta Tags Guide Source Control Guide: Team Accessibility Guide Foundation Server Analysis and Reports Guide Micro Content Guide Styles Guide Architecture Guide Navigation Links Guide Tables Guide Autonumbers Guide Plug-In API Guide Tables of Contents Guide Branding Guide Print-Based Output Guide Targets Guide Condition Tags Guide Project Creation Guide Template Pages Guide Context-Sensitive Help Guide QR Codes Guide Templates Guide Eclipse Help Guide Reviews & Contributions With Contributor Guide Topics Guide eLearning Guide Touring the Workspace Guide Scripting Guide Getting Started Guide Search Guide Transition From FrameMaker Global Project Linking Guide Guide SharePoint Guide HTML5 Guide Translation and Localization Skins Guide Guide Images Guide Snippets Guide Variables Guide Import Guide Source Control Guide: Git Videos Guide Indexing Guide Source Control Guide: What's New Guide Key Features Guide Perforce Helix Core Lists Guide Source Control Guide: Subversion MadCap Central Integration

APPENDIX 80